

How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

This site uses cookies for advertising. If you continue to use the site, you accept the use of cookies.[more info](#)

[jump to the content](#)

Gentoo.LinuxHowtos.org howtos, tips&tricks and tutorials for gentoo linux

from small one page howto to huge articles all in one place

Other [.linuxhowtos.org](#) sites:
[toolsntoys.linuxhowtos.org](#)

www.linuxhowtos.org

Last additions:

How to make X listen on port 6000

How to make X listen on port 6000

words:

34

views:

39914

userrating:

May, 25th 2007:

Words

496

why adblockers are bad

April, 26th 2007:

Words

77

Website translation planned

Apr, 10th. 2007:

Words

63

Compile Time Estimator integrated into genlop

[image:Druckversion](#) / [/data/printer.gif](#) (null)

How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

image:pdf icon / /data/pdf.png (null)

You are here:

ntp is the Network Time Protocol suite.

Installing ntpd

First, make sure ntp/ntpdate are installed. The package is by default installed on Mandrake Linux and Redhat. If you do not have ntp installed you will find packages on your distributions install-cd(s).

On Gentoo Linux, install by typing---

```
emerge ntp
```

Configuration files for running ntp as daemon

ntpd manpage

Client Setup

Now, edit the following files:

```
--- /etc/ntp.conf
```

The only important thing is that the line contains server some.thing.org.

Example:

```
---server ntp.uio.nodriftfile /etc/ntp/driftbroadcastdelay 0.008authenticate no---
```

Make sure you add ntpd as a boot (init) service.

Gentoo Linux: ``rc-update add ntpd default` , `/etc/init.d/ntpd start``

(LAN) Server setup

To run a ntp server to sync the clocks on your lan, edit

```
--- /etc/ntp.conf
```

Example:

```
---server fartein.ifi.uio.no preferserver ntp.uio.noserver ntp.eunet.no
```

```
fudge 10.0.0.50 stratum 10
```

```
driftfile /etc/ntp/driftbroadcastdelay 0.008
```

```
authenticate no---
```

fudge tells the server to pass on the correct time to the given network interface. stratum is the level of time servers, 10 being the lowest. You only need a higher number if you will be acting as a public internet timeserver with fast bandwidth.

It makes sence to add a few servers. Select the best as prefer

Make sure you add ntpd as a boot (init) service.

Gentoo Linux: ``rc-update add ntpd default` , `/etc/init.d/ntpd start``

Firewalls

ntp uses port 123, both UDP and TCP. Make sure this port is not blocked by a firewall.

If you are using iptables, you can open this port with

How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

```
--- $IPTABLES -A INPUT -j ACCEPT -p tcp --dport 123
```

Known valid and working ntp servers

server	adress	Location	ntp	ipv6	viagenie	qc	cal	PV6	ONLY	clock	via	netserver
--------	--------	----------	-----	------	----------	----	-----	-----	------	-------	-----	-----------

far	tein	.ifi	.uio	.no	Norway	server	ntp	.uio	.no	Norway	server	server
-----	------	------	------	-----	--------	--------	-----	------	-----	--------	--------	--------

How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

Server List

* <http://www.eecis.udel.edu/~mills/ntp/servers.html>

Setting the clock at boot or using cron

A good idea is not to run the ntpd daemon on clients as it uses about 1,7 MB memory, unless you are a server or have a box with a broken clock. Many boxes clocks do drift along on their own, a check every hour or day is generally a good idea.

rdate

rdate is a simple 3 kB tool for syncing the system clock to a server. It's options are `-p`` to print the date on the given server, `-s`` to set the system clock according to it (must be done as root) and `-u`` to use the UDP protocol. Example:

```
`rdate -p sntp.lth.se`
```

rdate manual page

clockspeed

clockspeed is a very small tool for setting the clock and is, for clients, a much better alternative than installing the 4+ MB ntp package.

* [clockspeed-0.62.tar.gz](#) 28K

cron & ntp

You can simply add ntpdate as a cron job every now and then:

```
--- echo 'ntpdate -b server.dot.com' > /etc/cron.hourly/time.cron--- chmod a+x  
/etc/cron.hourly/time.cron
```

Most distributions come with a cron. dcron and Vixie cron are nice.

Gentoo & ntp-client

You can set the clock using ntp at boot (without starting the daemon) on Gentoo Linux by editing:

```
--- /etc/conf.d/ntp-client
```

The file should contain:

```
---NTPDATE_CMD="ntpdate"NTPDATE_OPTS="-b your.server.here"---
```

Then add ntp-client to the services started at boot:

```
--- rc-update add ntp-client default
```

You can check what services are started at boot with ``rc-status``.

Page source:

* [t2t:ntp.t2t.tar.bz2](#)

Copyright (c) 2000-2004 Øyvind Sæther. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

Please read "Why adblockers are bad".

```
var google_ad_client = "pub-4309123515655559";
var google_alternate_color = "CCCCCC"; var google_ad_width = 160; var google_ad_height
= 600; var google_ad_format = "160x600_as"; var google_ad_channel = "3097575257"; var
google_color_border = "000000"; var google_color_text = "000000"; var google_color_bg =
"CCCCCC"; var google_color_link = "0000FF"; var google_color_url = "008000";
```

other Ads

<!--

Stellenangebote

Stellenangebote

für Fach- und

Führungskräfte

www.nachoben.com

-->

Trace My Cash

Wenn Sie sich schon immer mal gefragt haben, wo eigentlich Ihr geliebtes Bargeld geblieben ist, finden Sie hier vielleicht die Antwort.

www.tracemycash.com

Other free services

toURL.org

Shorten long

URLs to short

links like

<http://turl.org/2>

turl.org

.

Reverse DNS lookup

Find out which hostname(s)

resolve to a

given IP or other hostnames for the server

www.reversednslookup.org

New Packages

- as

image:rdf newsfeed / /data/rdf.png (null)

- as

image:rss newsfeed / /data/rss.png (null)

- as

image:Atom newsfeed / /data/atom.png (null)

How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

image:rdf newsfeed //data/rdf.png (null)

|

image:rss newsfeed //data/rss.png (null)

|

image:Atom newsfeed //data/atom.png (null)

- Powered by

image:LeopardCMS //data/leopardcms.png (null)

- Running on

image:Gentoo //data/gentoo.png (null)

-

Copyright 2004-2017 Sascha Nitsch Unternehmensberatung
UG(haftungsbeschänkt)

image:Valid XHTML1.1 //data/xhtml.png (null)

:

image:Valid CSS //data/css.png (null)

:

image:buttonmaker //data/buttonmaker.png (null)

- Level Triple-A Conformance to Web Content Accessibility Guidelines 1.0 -

- Copyright and legal notices -

Time to create this page: ms

image:system status display //status/output.jpg (null)

```
bodyloaded(); document.getElementById("fulltextsearch").onkeypress=chk;
```