

# How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

---

[jump to the content](#)

Gentoo.LinuxHowtos.org howtos, tips&tricks and tutorials for gentoo linux

from small one page howto to huge articles all in one place

Other .linuxhowtos.org sites:  
[toolsntoys.linuxhowtos.org](http://toolsntoys.linuxhowtos.org)

[www.linuxhowtos.org](http://www.linuxhowtos.org)

Last additions:

How to make X listen on port 6000

How to make X listen on port 6000

words:

34

views:

40903

userrating:

May, 25th 2007:

Words

496

why adblockers are bad

April, 26th 2007:

Words

77

Website translation planned

Apr, 10th. 2007:

Words

63

Compile Time Estimator integrated into genlop

image:Druckversion / /data/printer.gif (null)

image:pdf icon / /data/pdf.png (null)

# How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

---

You are here:

ntp is the Network Time Protocol suite.

## Installing ntpd

First, make sure ntp/ntpdate are installed. The package is by default installed on Mandrake Linux and Redhat. If you do not have ntp installed you will find packages on your distributions install-cd(s).

On Gentoo Linux, install by typing---

```
emerge ntp
```

## Configuration files for running ntp as daemon

ntpd manpage

### Client Setup

Now, edit the following files:

```
--- /etc/ntp.conf
```

The only important thing is that the line contains server some.thing.org.

Example:

```
---server ntp.uio.nodriftfile /etc/ntp/driftbroadcastdelay 0.008authenticate no---
```

Make sure you add ntpd as a boot (init) service.

Gentoo Linux: ``rc-update add ntpd default` , ` /etc/init.d/ntpd start``

### (LAN) Server setup

To run a ntp server to sync the clocks on your lan, edit

```
--- /etc/ntp.conf
```

Example:

```
---server fartein.ifi.uio.no preferserver ntp.uio.noserver ntp.eunet.no
```

```
fudge 10.0.0.50 stratum 10
```

```
driftfile /etc/ntp/driftbroadcastdelay 0.008
```

```
authenticate no---
```

fudge tells the server to pass on the correct time to the given network interface. stratum is the level of time servers, 10 being the lowest. You only need a higher number if you will be acting as a public internet timeserver with fast bandwidth.

It makes sense to add a few servers. Select the best as prefer

Make sure you add ntpd as a boot (init) service.

Gentoo Linux: ``rc-update add ntpd default` , ` /etc/init.d/ntpd start``

### Firewalls

ntp uses port 123, both UDP and TCP. Make sure this port is not blocked by a firewall.

If you are using iptables, you can open this port with

```
--- $IPTABLES -A INPUT -j ACCEPT -p tcp --dport 123
```

### Known valid and working ntp servers

# How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

---

server address Location ntp.ipv6.viagenie.qc.ca IPv6 ONLY clock.via.netserver  
fartein.ifi.uio.no Norwayserver ntp.uio.no Norwayserver

# How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

---

## Server List

\* <http://www.eecis.udel.edu/~mills/ntp/servers.html>

## Setting the clock at boot or using cron

A good idea is not to run the ntpd daemon on clients as it uses about 1,7 MB memory, unless you are a server or have a box with a broken clock. Many boxes clocks do drift along on their own, a check every hour or day is generally a good idea.

### rdate

rdate is a simple 3 kB tool for syncing the system clock to a server. It's options are `-p`` to print the date on the given server, `-s`` to set the system clock according to it (must be done as root) and `-u`` to use the UDP protocol. Example:

```
`rdate -p sntp.lth.se`
```

rdate manual page

### clockspeed

clockspeed is a very small tool for setting the clock and is, for clients, a much better alternative than installing the 4+ MB ntp package.

\* [clockspeed-0.62.tar.gz](#) 28K

## cron & ntp

You can simply add ntpdate as a cron job every now and then:

```
--- echo 'ntpdate -b server.dot.com' > /etc/cron.hourly/time.cron--- chmod a+x  
/etc/cron.hourly/time.cron
```

Most distributions come with a cron. dcron and Vixie cron are nice.

## Gentoo & ntp-client

You can set the clock using ntp at boot (without starting the daemon) on Gentoo Linux by editing:

```
--- /etc/conf.d/ntp-client
```

The file should contain:

```
---NTPDATE_CMD="ntpdate"NTPDATE_OPTS="-b your.server.here"---
```

Then add ntp-client to the services started at boot:

```
--- rc-update add ntp-client default
```

You can check what services are started at boot with ``rc-status``.

Page source:

\* [t2t:ntp.t2t.tar.bz2](#)

Copyright (c) 2000-2004 Øyvind Sæther. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

# How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

---

## Other free services

toURL.org

Shorten long

URLs to short

links like

<http://turl.org/2>

[turl.org](http://turl.org)

.

## Reverse DNS lookup

Find out which hostname(s)

resolve to a

given IP or other hostnames for the server

[www.reversednslookup.org](http://www.reversednslookup.org)

## New Packages

- as

image:rdf newsfeed //data/rdf.png (null)

- as

image:rss newsfeed //data/rss.png (null)

- as

image:Atom newsfeed //data/atom.png (null)

image:rdf newsfeed //data/rdf.png (null)

|

image:rss newsfeed //data/rss.png (null)

|

image:Atom newsfeed //data/atom.png (null)

- Powered by

image:LeopardCMS //data/leopardcms.png (null)

- Running on

image:Gentoo //data/gentoo.png (null)

-

Copyright 2004-2018 Sascha Nitsch Unternehmensberatung  
UG(haftungsbesch&auml;nkt)

# How to make X listen on port 6000

<http://gentoo.linuxhowtos.org/ntp/ntp.pdf>

---

image:Valid XHTML1.1 //data/xhtml.png (null)

:

image:Valid CSS //data/css.png (null)

:

image:buttonmaker //data/buttonmaker.png (null)

- Level Triple-A Conformance to Web Content Accessibility Guidelines 1.0 -

- Copyright and legal notices -

Time to create this page: ms

<!--

image:system status display //status/output.jpg (null)

-->

bodyloaded();